

HOW TO PUT THE MAPS FIX ON YOUR 911 REALITY SIMULATOR

STEP 1 Locate your custom addressing called ali.mbd(MS ACCESS)

You can copy your current addressing from the Instructor station

C:/Program Files / ARTComms copy ali.mbd to your desktop to drag back to the same file after installing the exe file. The exe puts Anytown default back on your station.

STEP 2 Download the **Ali.zip** files from the Dropbox link and put the file on a flash drive. Extract the zip to find **setup_plus_v1.5.7.5.exe** Take the flash drive to your instructor and student. Do not open the Reality Software using Start Simulation.

STEP 3 Use **Setup_plus_v1.5.7.5.exe** install for instructor and student - appropriately pull down the menu to say Instructor or Student on the correct station. No to another icon. Finish.

STEP 4 If customized now return your **ALI.mbd** on your desktop to replace the default in C:/Program Files / ARTComms - replace the current ali.mbd? **YES.**

STEP 5 You may have your custom Call Types in C:/Installation Folder. Contact support@911trainer.com to ask if we stored your Types and Units.xls file. To install custom CALL TYPES/UNITS use SIMULATION DATABASE MANAGER (this is currently installed on all stations). See Instructions in Customizing folder on your desktop or call and we will walk you through this process.

STEP 6 Reboot and test to ensure your mapping is working correctly.

